

vIP-FileTransfer Large-Volume File Transmission Service

CLIENT SOFTWARE INSTALLATION GUIDE

Table of Content

1	vIP-FileTransfer Service.....	3
2	Software Download	3
3	Installation of VFT	5
3.1	Additional Installation Procedures.....	8
4	Uninstallation of VFT	11
5	System Requirement:	12


1 vIP-FileTransfer Service

To start using the Large-volume File Transmission Service, client software, vIP-FileTransfer (VFT), has to be installed.


2 Software Download

To download client software, please go to <http://vipft.ntt.com.hk>


Then, press on the following button.



Click [Save] button




Then, choose the directory to save the file and press [Save] button.



3 Installation of VFT

First, extract “VFT_v2.1a.zip” to a particular folder.

In that particular folder, go to folder “VFT_v2.1a”. Then, double click “setup.bat” to execute the installation.



Read the license agreement.

Then, click [YES] to accept the agreement and continue installation.

If you do not accept the agreement, click [NO] to exit installation.


In ❶, the default destination folder for installation is “C:\Program Files\VFT”. It can be changed by clicking [Browse] button.
(if the default destination folder for installation is changed, please also follows the additional installation procedures in section 3.1)

In ❷, please select your preferred language (English, Japanese, Simplified or Traditional Chinese) for the client software.


In ❸, select [Yes] to create a desktop shortcut. Select [No] to skip the creation of desktop shortcut.

Then, click [Install] button to continue the installation.


Otherwise, click [Cancel] to terminate the installation or click [Return] to go back to License Agreement page.




Click [Yes] to start installation. Please be patient during installation, it may takes a few minutes depends on your system configuration.




Click [Yes] to add information in registry.



Click [OK] to continue.




Press [OK] button to complete the installation.



3.1 Additional Installation Procedures


This procedure is required only for users who have changed the default destination folder for installation.

For example, the destination folder for installation is changed to “C:\VFT_Test”




After installation completed, please go to the folder extracted from “VFT_v2.1a.zip”.
(i.e. “C:\...\VFT_v2.1a”)

Right click on “ca.cer”, then click [Copy].




Then, go to your destination folder for installation and go to folder “C:\...\cert\ca”.
(In our example, go to “C:\VFT_Test\cert\ca”)

On the white space, right click and then press [Paste].




Then, press [Yes] to replace the file and installation additional procedure is completed.




4 Uninstallation of VFT

Go to “C:\Program Files\VFT\bin” or the directory that VFT is installed and go to the folder “bin”.


Double click [uninstaller.bat] to execute the uninstallation.



Click [OK] to confirm the uninstallation of VFT.
Otherwise, click [Cancel] to exit uninstallation.



Click [OK] to complete the uninstallation process.



5 System Requirement

OS	Windows XP Professional SP2 Windows XP Home SP2 Windows 2000 Professional SP4
-----------	---

Recommended software configuration

* Java VM (JRE 1.4.2_11) will be installed automatically with the client software.

CPU	Pentium3 1GHz or above
Memory	256Mb or above

Recommended hardware configuration